

!A

*** End of Pass 1

*** End of Pass 2

```

0800          1          ttl "Print Version Test, VERSION.L"
0800          2          ;
0800          3          ;
0800          4          ; VERSION.L
0800          5          ;
0800          6          ;
0800          7          enz
0800          8          ;
0000          9  ZERO      equ $00
0080         10  ASCIFLAG  equ $80
00FF         11  NEGONE    equ $FF
0800         12          ;
03E1         13  RDCLKVSN  equ $3E1
0800         14          ;
FD8E         15  CROUT     equ $FD8E
FDED         16  COUT      equ $FDED
0800         17          ;
0800         18          ;
0900         19          org $900
0900         20          obj $900
0900         21          usr
0900         22          ;
0900         23          ;
0900 A0 2E     24          ldy #BUFFER
0902 A9 09     25          lda /BUFFER
0904         26          ;
0904 20 2A 09  27          jsr READVSN
0907         28          ;
0907 20 8E FD  29          jsr CROUT
090A 20 8E FD  30          jsr CROUT
090D         31          ;
090D A9 AA     32          lda #"*"
090F 20 ED FD  33          jsr COUT
0912         34          ;
0912 A0 00     35          ldy #ZERO
0914         36          ;
0914 B9 2E 09  37  ^1     lda BUFFER,Y
0917 F0 08     38          beq >2
0919         39          ;
0919 09 80     40          ora #ASCIFLAG
091B         41          ;
091B 20 ED FD  42          jsr COUT
091E         43          ;
091E C8        44          iny
091F D0 F3     45          bne <1          ; always taken
0921         46          ;
0921 A9 AA     47  ^2     lda #"*"
0923 20 ED FD  48          jsr COUT
0926         49          ;
0926 20 8E FD  50          jsr CROUT
0929         51          ;
0929 60        52          rts
092A         53          ;
092A         54          ;
092A 38        55  READVSN  sec
092B         56          ;
092B 6C E1 03  57          jmp (RDCLKVSN)
092E         58          ;
092E         59          ;
092E         60  BUFFER    dfs 21,ZERO

```

0943 61 ;
0943 62 ;

BSAVE VERSION,A\$0900,B,L\$0043

0943 63 usr VERSION
0943 64 ;
0943 65 ;
0943 66 end 111

*** End of Assembly

Symbol List starts at 0x7800, ends at 0x7864, used 0x0064, remaining 0x3F94

Symbols unsorted:

ZERO	0000	ASCIFLAG	0080	NEGONE	00FF	RDCLKVSN	03E1	CROUT	FD8E
COUT	FDED	READVSN	092A	BUFFER	092E				

Symbols alphabetically sorted:

ASCIFLAG	0080	BUFFER	092E	COUT	FDED	CROUT	FD8E	NEGONE	00FF
RDCLKVSN	03E1	READVSN	092A	ZERO	0000				

Symbols numerically sorted:

ZERO	0000	ASCIFLAG	0080	NEGONE	00FF	RDCLKVSN	03E1	READVSN	092A
BUFFER	092E	CROUT	FD8E	COUT	FDED				